



Basic config CISCO

Unconfigured Router

```
Cisco CISCO2911/K9 (revision 1.0) with 491520K/32768K bytes of memory.  
Processor board ID FTX152400KS  
3 Gigabit Ethernet interfaces  
4 Low-speed serial(sync/async) network interface(s)  
DRAM configuration is 64 bits wide with parity disabled.  
255K bytes of non-volatile configuration memory.  
249856K bytes of ATA System CompactFlash 0 (Read/Write)
```

--- System Configuration Dialog ---

Continue with configuration dialog? [yes/no]:

Configured Router

```
Cisco CISCO2911/K9 (revision 1.0) with 491520K/32768K bytes of memory.  
Processor board ID FTX152400KS  
3 Gigabit Ethernet interfaces  
4 Low-speed serial(sync/async) network interface(s)  
DRAM configuration is 64 bits wide with parity disabled.  
255K bytes of non-volatile configuration memory.  
249856K bytes of ATA System CompactFlash 0 (Read/Write)
```

Press RETURN to get started!

Jodoi-Router>

Basic config CISCO

Logging in to the Cisco Router

```
User Access Verification
```

```
Password:
```

```
Password:
```

```
Jodoi-Router> ————— User-Mode Prompt
```

```
Jodoi-Router>enable
```

```
Jodoi-Router#
```

```
Jodoi-Router# ————— Privileged-Mode Prompt
```

```
Jodoi-Router#disable
```

```
Jodoi-Router>
```

```
Jodoi-Router>logout
```

Basic config CISCO

Logging in to the Cisco Router

```
Jodoi-Router>enable
Jodoi-Router#
Jodoi-Router#configure terminal
Enter configuration commands, one per line.  End with CNTL/Z.
Jodoi-Router(config)# Global Configuration Mode
Jodoi-Router(config)#interface gigabitEthernet 0/0
Jodoi-Router(config-if)#exit
Jodoi-Router(config)#
Jodoi-Router(config)#
Jodoi-Router(config)#
Jodoi-Router(config)#line console 0
Jodoi-Router(config-line)#exit
Jodoi-Router(config)#
Jodoi-Router(config)#interface g0/0.1
Jodoi-Router(config-subif)#
Jodoi-Router(config-subif)#
```

Basic config CISCO

Banner , Save , Reboot Cisco Router

```
Jodoi-Router(config)#banner motd 1
Enter TEXT message. End with the character '1'.
#####
###          Jodoi-Router          ###
#####
1                                     Banner

Jodoi-Router(config)#exit
Jodoi-Router#
%SYS-5-CONFIG_I: Configured from console by console

Jodoi-Router#
Jodoi-Router#
Jodoi-Router#copy running-config startup-config ——— Save
Destination filename [startup-config]?
Building configuration...
[OK]
Jodoi-Router#reload ——— Reboot
Proceed with reload? [confirm]|
```